

CA Release Automation - Integrations F5 BIG-IP

Date: 26-Jul-2016



CA Release Automation - Integrations

This Documentation, which includes embedded help systems and electronically distributed materials, (hereinafter referred to as the "Documentation") is for your informational purposes only and is subject to change or withdrawal by CA at any time. This Documentation is proprietary information of CA and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of CA.

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all CA copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to CA that all copies and partial copies of the Documentation have been returned to CA or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, CA PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL CA BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF CA IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is CA.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19(c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2016 CA. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

Table of Contents

Action Pack for F5 BIG-IP 10.5.1410	7
What's New	8
Install the Action Pack	9
Prerequisites to Run F5 BIG-IP Actions	10
F5 BIG-IP Actions	11
F5-Add Member to Global Pool	11
F5-Add Member to Pool	11
F5-Change Global Pool Member Settings	12
F5-Change Pool Member Settings	12
F5-ConfigSync	13
F5-Create Global iRule	13
F5-Create Global Pool	14
F5-Create iRule	14
F5-Create Pool	14
F5-Delete Global iRule	15
F5-Delete Global Pool	15
F5-Delete iRule	16
F5-Delete Pool	16
F5-Disable iRule	16
F5-Disable Member	17
F5-Enable iRule	17
F5-Enable Member	18
F5-Get Failover State	18
F5-Get Global Pool Member State	19
F5-Get Global Pool Member Number of Connections	20

F5-Get Global Pool Status	20
F5-Get Local Pool Status	21
F5-Get Pool Member State	21
F5-Get Pool Member Number of Connections	22
F5-List All Global Pool Members	22
F5-List All Global Pools	23
F5-List All Pool Members	23
F5-List All Pools	24
F5-List Virtual Server iRules	24
F5-Remove Member from Global Pool	25
F5-Remove Member from Pool	25
F5-Retrieve Global iRule Definition	26
F5-Retrieve iRule Definition	26
F5-Set Global Pool Member State	27
F5-Set Global Pool State	27
F5-Set iRule Priority	27
F5-Set Pool Member State	28
F5-Update Global iRule Definition	28
F5-Update iRule Definition	29

F5 BIG-IP

Action Pack for F5 BIG-IP 10.5.1410

The Action Pack for F5 BIG-IP contains actions that enable you to create processes that perform operations in F5 BIG-IP.

Actions Help

For a list of input and output descriptions for deployed actions, refer to the embedded actions help that is available in the installation at:

- [F5 BIG-IP Actions \(see page \)](#) in this document
- <http://nolio-app/actionshelp.jsp> in your deployment after you deploy the action pack.

Supported Platforms:

- F5 BIG-IP actions in this pack support the F5 platform 11.5 and 10.2
- F5 BIG-IP actions in this pack support CA Release Automation 5.0 and later
- Windows 2008 R2 and Linux Red Hat 6

Supported Transport Protocols

Release Automation is a client of the F5 BIG-IP Management Console API. The F5 BIG-IP actions connect with the F5 BIG-IP Management Console API using the iControl interface. Because F5-iControl supports HTTP and HTTPS, Release Automation actions support HTTP and HTTPS.

What's New

The following update was made for 10.5.1410

- Updated the action "F5-Set Pool Member State" partition search. Searches the correct partition for pool members.
- F5 Big-IP actions now accepts the value of "0" (zero) as the port number in the Member Port field.

Install the Action Pack

Install and use these actions to execute commands and tasks in F5 BIG-IP.

Follow these steps:

1. Verify the [Prerequisites to Run F5 BIG-IP Actions \(see page 10\)](#).
2. Deploy the action pack for F5 BIG-IP.
For more information, see [Manage Action Packs and Plug-ins \(https://docops.ca.com/display/RAINT/Manage+Action+Packs+and+Plug-ins\)](https://docops.ca.com/display/RAINT/Manage+Action+Packs+and+Plug-ins).
3. Use F5 BIG-IP actions in CA Release Automation processes.

Prerequisites to Run F5 BIG-IP Actions

To run F5 BIG-IP actions, verify the following prerequisites:

Certificates

Release Automation uses a web-service client that runs on a JVM.

- If the F5 server listens over https, then store the corresponding certificates in a JVM Keystore.
- If Release Automation runs in a multi-JVM environment, then store the certificates in the same JVM used by Release Automation.

Dependencies

- Download and import the the Action Pack:
 1. Download the action pack from [CA Support \(http://support.ca.com\)](http://support.ca.com).
 2. Extract the Action Pack zip file to get the action pack .jar and the dependencies .zip files.
 3. Extract the dependencies.zip file.
 4. Import both the .jar and the contents of the dependencies .zip into CA Release Automation using Actions Management.
- When the action pack manager deploys the F5 BIG-IP action pack, the requisite jar file dependencies are automatically downloaded to the actionLibs directory.
- The exception is the iControl.jar file, import this file manually.

Follow these steps:

1. Download the iControl.jar file to your local drive from <https://devcentral.f5.com/d/icontrol-library-for-java-source>. (<https://devcentral.f5.com/d/icontrol-library-for-java-source>)
2. Launch Automation Studio.
3. Under the Administration tab, click Actions Management.
4. Click the Import Action Package icon.
5. Navigate to the downloaded version of the iControl.jar file.
6. Click Open, verify your selection, and then click Import.

F5 BIG-IP Actions

The F5 BIG-IP Action Pack provides the following actions:

F5-Add Member to Global Pool

Adds new member to the specified global pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Add Member to Pool

Adds new member to the specified pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Change Global Pool Member Settings

Changes global pool member settings for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Passwo rd	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition
Ratio	Integer	The new global pool member ratio value. It should be an integer within the range[1..100]

F5-Change Pool Member Settings

Changes pool member settings for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Passw ord	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
Connection Limit	Long	The new pool member connection limit. It should be an integer within the range[0..45645656456]
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.

Name	Type	Description
Partition Name	String	The name of the active partition
Priority Group	Integer	The new pool member priority group. It should be an integer within the range [0 - 65,535]
Ratio	Integer	The new pool member ratio value. It should be an integer within the range[1..100]

F5-ConfigSync

Runs config sync.

Input Values

Name	Type	Description
* Config Sync Type	ConfigSyncAction\$ConfigSyncType	Type of synchronization to do. From group or to Group
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Group	String	The group to synchronize to/from
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.

F5-Create Global iRule

Creates a new global iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* I Rule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
I Rule Definition	String	Global iRule Definition
Partition Name	String	The name of the active partition

F5-Create Global Pool

Creates new global pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the new global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Initial Member Address	String	The IP address of the virtual server for the initial global pool member.
Initial Member Port	Integer	The port of the virtual server for the initial global pool member.
LB Method : Prefered (GTLB Method Type)	GTLBPreferredMethodType	The name of the preferred global load balancing method.
Partition Name	String	The name of the active partition

F5-Create iRule

Creates a new iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* iRule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
iRule Definition	String	iRule Definition
Partition Name	String	The name of the active partition

F5-Create Pool

Creates a new pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the new pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Initial Address	String	The IP address of the initial pool member.
Initial Port	Integer	The port of the initial pool member.
LB Method	LBMethodType	The name of the load balancing method.
LBMethod (deprecated)	String	Deprecated - use LBMethod instead.
Partition Name	String	The name of the active partition

F5-Delete Global iRule

Deletes a Global iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* I Rule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Delete Global Pool

Deletes the specified global pool from F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.

Name	Type	Description
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Delete iRule

Deletes an iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* iRule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Delete Pool

Deletes the specified pool from F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Disable iRule

Disables the requested iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Fail If Already Disabled	BIG-IPBoolean	Fail action if the specified iRule already disabled.
* iRule Name	String	iRule Name.
* Virtual Server Name	String	Virtual Server name.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Disable Member

Set the monitor state of the specified member to Disabled.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Enable iRule

Enables the requested iRule.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
		The log in name to the F5 management console.

Name	Type	Description
* F5 User Name	String	
* Fail If Already Enabled	Boolean	Fail action if the specified iRule already enabled.
* iRule Name	String	iRule Name.
* Virtual Server Name	String	Virtual Server name.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
iRule Priority	Long	Priority for the iRule that we are trying to enable(Non-negative number, starting from 0). By default,the iRule would be added at the bottom of the iRules list.
Partition Name	String	The name of the active partition

F5-Enable Member

Set the monitor state of the specified member to Disabled.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Get Failover State

Retrieves the Failover state.

Input Values

Name	Type	Description
	String	The IP address of the F5 BIG-IP management console.

Name	Type	Description
* F5 Mngmnt IP		
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
Expected State	FailoverStateEnum	Expected state. Action fails if actual failover state does not match the expected one.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.

Output Values

Name	Type	Description
State	FailoverStateEnum	State

F5-Get Global Pool Member State

Retrieves the state of a global pool member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Description	String	Textual description of state as provided by f5
State	String	State

F5-Get Global Pool Member Number of Connections

Retrieves the number of currently active connections to a global pool member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Connections	long	Number of connections to global pool member

F5-Get Global Pool Status

Retrieves the status of a global pool.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Availability State	String	Pool Available State
Description	String	Textual description of state as provided by f5
Pool State	String	Pool State

F5-Get Local Pool Status

Retrieves the status of a local pool.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Availability State	String	Pool Available State
Description	String	Textual description of state as provided by f5
Pool State	String	Pool State

F5-Get Pool Member State

Retrieves the state of a pool member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.

F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Description	String	Textual description of state as provided by f5
State	String	State

F5-Get Pool Member Number of Connections

Retrieves the number of currently active connections to a pool member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Connections	long	Number of connections to Pool Member

F5-List All Global Pool Members

Enumerates members of the specified global pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console

Name	Type	Description
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Member Addresses	String[]	The IP addresses of pool members.
Member Ports	Integer[]	Ports of pool members.

F5-List All Global Pools

Enumerates all global pools for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Pool Names	String[]	The name of the global pool.

F5-List All Pool Members

Enumerates members of the specified pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.

Name	Type	Description
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Member Addresses	String[]	The IP addresses of pool members.
Member Ports	Integer[]	Ports of pool members.

F5-List All Pools

Enumerates all pools for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
Pool Names	String[]	The name of the pool.

F5-List Virtual Server iRules

Retrieves a list of iRules enabled for a specific virtual server.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Virtual Server Name	String	Virtual Server name.

Name	Type	Description
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
iRule Names	String[]	iRule Names

F5-Remove Member from Global Pool

Removes the specified member from the specified global pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Remove Member from Pool

Removes the specified member from the specified pool for F5 BIG-IP.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.

Name	Type	Description
Partition Name	String	The name of the active partition

F5-Retrieve Global iRule Definition

Retrieves a global iRule definition.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* I Rule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
I Rule Definition	String	Global iRule Definition

F5-Retrieve iRule Definition

Retrieves an iRule definition.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* iRule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

Output Values

Name	Type	Description
iRule Definition	String	iRule Definition

F5-Set Global Pool Member State

Set the state of a global pool member, to enable, or disable a member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of virtual server for the global pool member.
* Member Port	Integer	Port of virtual server for the global pool member.
* Pool Name	String	The name of the global pool.
* State	GTStateEnum	State
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Set Global Pool State

Change state of a global pool.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Pool Name	String	The name of the global pool.
* State	PoolStateEnum	State
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Set iRule Priority

Changes the priority of an iRule in a virtual server.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* iRule Name	String	iRule Name.
* iRule Priority	Long	New priority for iRule (Non-negative number, starting from 0).
* Virtual Server Name	String	Virtual Server name.
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Set Pool Member State

Sets the status of a pool member.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* Member Address	String	The IP address of the pool member.
* Member Port	Integer	Port of the pool member.
* Pool Name	String	The name of the pool.
* State	StateEnum	State
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Update Global iRule Definition

Updates an existing global iRule definitions.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 BIG-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.

Name	Type	Description
* I Rule Definition	String	Global iRule Definition
* I Rule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 BIG-IP management console.
Partition Name	String	The name of the active partition

F5-Update iRule Definition

Updates an existing iRule's definitions.

Input Values

Name	Type	Description
* F5 Mngmnt IP	String	The IP address of the F5 Big-IP management console.
* F5 Password	Password	The password to log in the F5 management console
* F5 User Name	String	The log in name to the F5 management console.
* iRule Definition	String	iRule Definition
* iRule Name	String	iRule Name
F5 Mngmnt Port	Integer	The port to the F5 Big-IP management console.
Partition Name	String	The name of the active partition